


# Mackay Meters - Permit Push/Export Integration

OPS-COM supports exporting temp, standard, and validation permits purchased in OPS-COM to MacKay Meters.

There are a few system and lot configurations to setup before this works with you Mackay Meters system. The article assumes you already have a MacKay Meters environment and logins details (username & password), if you don't please contact your MacKay Meters representative to obtain them and let us (OPS-COM) know if you have any questions or concerns about this integration.

## Tools → View System Task Logs:



### Scheduled Tasks

Recurring Tasks						
Task	Enabled	Next Fire Time	Last Fire Time	Frequency	Logs	Stats ?
<a href="#">Run</a> <a href="#">Export To Mackay Meters</a>	<a href="#">✓ Enabled</a>	Never	Never	Every 5 minutes	<a href="#">Logs</a>	

You may not see this system task and currently only OPS-COM staff can enable it. Please contact us if you require this setup. This system task is used to check OPS-COM permits for any that need to be pushed/exported to MacKay Meters.

# System Configuration/Settings:

## System Configuration → System Settings → Third Party:

As mentioned above you should have some sort of MacKay meters login details. This is where you set them:

\*Note: There are test and none-test (production/live) fields. Depending on the domain you're using to run your tests OPS-COM will either use the username and password fields for production, and test username and test password for preview/testing.


Preview/test domains look like this:

something.**preview**.ops-com.com

something-**test**.**preview**.ops-com.com

Production domains look like this:

something.ops-com.com



## System Configuration → Parking → Mange Lot Zones:

Zone names needs to be exactly what is set in MacKay Meters, if you don't know what the zone name should be please ask MacKay Meters or OPS-COM.

The screenshot shows the 'Manage Lot Zones' page. On the left, the 'Parking' menu item is highlighted, leading to 'Manage Lot Zones'. An arrow points from this menu item to the 'MacKay-Meters' zone in the table. Another arrow points from the 'Add Lot Zone' button to a callout box. The table lists zones with columns for Name, Short Name, and actions (Edit, Delete). The 'MacKay-Meters' zone is highlighted as an example. The callout box contains the following text:

Create a new zone for permits/lots you wish to export to MacKay Meters.  
**\*IMPORTANT\***  
You must name the zone exactly what it is in MacKay meters, if you aren't sure what the zone (s) are called please ask OPS-COM support and/or MacKay Meters.

## Parking Management → Lot Administration → Pricing & Lot Admin:

Click into the lot you wish to add to the MacKay Meters zone (s), which in this example is "**MacKay-Meters**" in this example, then go under the "Zone & Location" tab and set the zone:

The screenshot shows the 'Edit Lot' page for 'Blue Tennent Lot - \$0.00'. The 'Zone & Location' tab is selected. Arrows point from the 'Lot Administration' menu to 'Pricing & Lot Admin' and then to the 'Zone & Location' tab. Another arrow points from the 'Zone' dropdown menu to the 'MacKay-Meters' zone. A callout box contains the following text:

Set the day and time values to whatever make sense for your business. These settings control whether permits in the zone are valid and on what days/time

Revision #2

Created 27 May 2024 11:21:59

Updated 11 September 2024 13:40:49