


Mackay Meters - Permit Push/Export Integration

OPS-COM supports exporting temp, standard, and validation permits purchased in OPS-COM to MacKay Meters.

There are a few system and lot configurations to setup before this works with you Mackay Meters system. The article assumes you already have a MacKay Meters environment and logins details (username & password), if you don't please contact your MacKay Meters representative to obtain them and let us (OPS-COM) know if you have any questions or concerns about this integration.

Tools → View System Task Logs:



Scheduled Tasks

Recurring Tasks						
Task	Enabled	Next Fire Time	Last Fire Time	Frequency	Logs	Stats ?
Run Export To Mackay Meters	✓ Enabled	Never	Never	Every 5 minutes	Logs	

You may not see this system task and currently only OPS-COM staff can enable it. Please contact us if you require this setup. This system task is used to check OPS-COM permits for any that need to be pushed/exported to MacKay Meters.

System Configuration/Settings:

System Configuration → System Settings → Third Party:

As mentioned above you should have some sort of MacKay meters login details. This is where you set them:

*Note: There are test and none-test (production/live) fields. Depending on the domain you're using to run your tests OPS-COM will either use the username and password fields for production, and test username and test password for preview/testing.


Preview/test domains look like this:

something.**preview**.ops-com.com

something-**test**.**preview**.ops-com.com

Production domains look like this:

something.ops-com.com



System Configuration → Parking → Mange Lot Zones:

Zone names needs to be exactly what is set in MacKay Meters, if you don't know what the zone name should be please ask MacKay Meters or OPS-COM.

The screenshot shows the 'Manage Lot Zones' page. On the left, the 'Parking' menu item is highlighted, leading to 'Manage Lot Zones'. An arrow points from 'MacKay-Meters' in the table to the 'Add Lot Zone' button. A callout box states: 'Create a new zone for permits/lots you wish to export to MacKay Meters. *IMPORTANT* You must name the zone exactly what it is in MacKay meters, if you aren't sure what the zone (s) are called please ask OPS-COM support and/or MacKay Meters.'

Name	Short Name	Edit	Delete
MacKay-Meters		Edit	Delete
Public		Edit	4 records.
RSL		Edit	2 records.
TLT		Edit	1 record.
Weekend Parking		Edit	1 record.

Parking Management → Lot Administration → Pricing & Lot Admin:

Click into the lot you wish to add to the MacKay Meters zone (s), which in this example is "**MacKay-Meters**" in this example, then go under the "Zone & Location" tab and set the zone:

The screenshot shows the 'Edit Lot' page for 'Blue Tennent Lot - \$0.00'. The 'Zone & Location' tab is active. Arrows point from 'Lot Administration' in the sidebar to 'Pricing & Lot Admin', and then to the 'Zone & Location' tab. A callout box states: 'Set the day and time values to whatever make sense for your business. These settings control whether permits in the zone are valid and on what days/time'.

Zone	Days of	Start Time	End Time	Remove Zone
MacKay-Meters	S M T W T F S	00:00	23:59	Remove Zone

Revision #2

Created 27 May 2024 11:21:59

Updated 11 September 2024 13:40:49