


Mackay Meters - Permit Push/Export Integration

OPS-COM supports exporting temp, standard, and validation permits purchased in OPS-COM to MacKay Meters.

There are a few system and lot configurations to setup before this works with you Mackay Meters system. The article assumes you already have a MacKay Meters environment and logins details (username & password), if you don't please contact your MacKay Meters representative to obtain them and let us (OPS-COM) know if you have any questions or concerns about this integration.

Tools → View System Task Logs:



Scheduled Tasks

Recurring Tasks						
Task	Enabled	Next Fire Time	Last Fire Time	Frequency	Logs	Stats ?
Run Export To Mackay Meters	✓ Enabled	Never	Never	Every 5 minutes	Logs	

You may not see this system task and currently only OPS-COM staff can enable it. Please contact us if you require this setup. This system task is used to check OPS-COM permits for any that need to be pushed/exported to MacKay Meters.

System Configuration/Settings:

System Configuration → System Settings → Third Party:

As mentioned above you should have some sort of MacKay meters login details. This is where you set them:

*Note: There are test and none-test (production/live) fields. Depending on the domain you're using to run your tests OPS-COM will either use the username and password fields for production, and test username and test password for preview/testing.


Preview/test domains look like this:

something.**preview**.ops-com.com

something-**test**.**preview**.ops-com.com

Production domains look like this:

something.ops-com.com



System Configuration → Parking → Manage Lot Zones:

Zone names needs to be exactly what is set in MacKay Meters, if you don't know what the zone name should be please ask MacKay Meters or OPS-COM.

The screenshot shows the 'Manage Lot Zones' page. On the left, the 'Parking' menu item is highlighted, leading to a sub-menu where 'Manage Lot Zones' is selected. An arrow points from this menu to the 'Add Lot Zone' button at the top right of the main content area. The main content area features a table with columns 'Name' and 'Short Name'. The first row, 'MacKay-Meters', is highlighted with a callout box stating 'Example zone created'. The 'Add Lot Zone' button is also highlighted with a callout box containing the following text:

Create a new zone for permits/lots you wish to export to MacKay Meters.
IMPORTANT
You must name the zone exactly what it is in MacKay meters, if you aren't sure what the zone (s) are called please ask OPS-COM support and/or MacKay Meters.

Name	Short Name	Edit	Delete
MacKay-Meters		Edit	Delete
Public		Edit	4 records.
RSL		Edit	2 records.
TLT		Edit	1 record.
Weekend Parking		Edit	1 record.

Parking Management → Lot Administration → Pricing & Lot Admin:

Click into the lot you wish to add to the MacKay Meters zone (s), which in this example is "**MacKay-Meters**" in this example, then go under the "Zone & Location" tab and set the zone:

The screenshot shows the 'Edit Lot' page for 'Blue Tennent Lot - \$0.00'. The left sidebar shows 'Lot Administration' selected, leading to 'Pricing & Lot Admin'. The main content area has tabs for 'General', 'Zone & Location', 'Standard Permits', 'Temporary Permits', 'LPR Settings', and 'Additional Settings'. The 'Zone & Location' tab is active. It shows a 'Location' field with 'Beside Main Campus Building' and an 'Image' field with a 'Select' button. Below this, there's a 'Zone' dropdown set to 'MacKay-Meters' and a 'Days of' section with a callout box stating: 'Set the day and time values to whatever make sense for your business. These settings control whether permits in the zone are valid and on what days/time'. The 'Days of' section shows a calendar grid with 'S' (Sunday) selected. The 'Start Time' is '00:00' and the 'End Time' is '23:59'. There are 'Add Zone By Days' and 'Add Zone By Date Range' buttons at the bottom.

Revision #3

Created 27 May 2024 11:21:59

Updated 4 June 2025 12:47:44 by Cedar Boulianne