

Mistall - Setup & Functionality

Overview

Mistall is a service that is used to count cars in a physical lot, using cameras to track vehicles as they enter and exit the lot.

Within the OPS-COM system, each Mistall lot is associated to a Lot Group.

Mistall Credentials

Mistall credentials need to be entered in system settings under third-party settings to be able to use the API.

Credentials are provided to the the client by Mistall itself.

Mistall APIs

Auth credentials for accessing Mistall API information.

✓ Enable Mistall Usage

Mistall Username

Mistall Password

Mistall X-Functions-Key

Save Settings

Lot Groups

The Lot Groups page was updated to accommodate the use of Mistall.

In addition, Lot Groups have replaced the use of Lots on the Real-Time map on both the admin and user sides.

To have data populate the Mistall Lot ID dropdown, the Update Mistall System Job Task must be run at least once to import the data into the system.

Columns have been added for setup with the Real-Time Map and Mistall data.

- Map color - map icon color
- Latitude and longitude - location on the map, selected by putting a point on the map
- Show on map - if the group will appear on the real-time map
- Mistall Lot ID - which Mistall lot the Lot Group correlates to

| Manage Parking Lot Groups | | | | | | | | | |
|---------------------------|--------------|---------------|----------------|-------------|----------|-----------|-----------|---|-------------|
| Name | Free Parking | Vehicle Count | Mistall Lot ID | Show on Map | Latitude | Longitude | Map Color | Usage | |
| ADA | 10 minutes | | 5441 | Yes | 45.14 | -76.14 | grey | Red Staff Lot West Blue Staff Lot Blue Tennent Lot ADA Temp Lot Omega Temp | Edit Delete |
| Bike1 | 0 minutes | | | Yes | 45.14 | -76.15 | green | The Bicycle Lot 1 | Edit Delete |
| BSL | 0 minutes | | | Yes | | | red | | Edit Delete |
| BSL2 | 0 minutes | | | No | 43.82 | -79.92 | blue | | Edit Delete |
| DRL | 0 minutes | 4 | | No | | | red | Physician Lot | Edit Delete |
| GML1 | 0 minutes | | | No | | | | | Edit Delete |
| GOL | 4 minutes | 5 | | No | 45.15 | -76.15 | blue | | Edit Delete |
| GSL | 0 minutes | | | No | | | | Green Staff Lot East | Edit Delete |
| Main | 6 minutes | 6 | | No | 45.14 | -76.15 | black | | Edit Delete |
| MSR | 0 minutes | | | No | | | | Main Street Residents | Edit Delete |

Lot Groups

Lot Group

ADA

Free Parking

10

Vehicle Count

Mistall Zone ID

5441 : Parking Garage

Show on Real-Time Map

Map

Map

Group Marker

Color

grey

Latitude

45.1404365157632

Longitude

-76.1447158158691

Click and drag the map marker to an appropriate map location.

Close

Save Changes


Lot Group page updates.

The updated lot group edit pop-up.

Lot Edit

On the lot edit page, the selection to set the lot group of the lot has been moved from the LPR section to the general section.

This is to allow clients who are not using the LPR system to still use the real-time map features.



The screenshot shows the 'Edit Lot' interface. At the top, there is a 'Back' button and a title 'Edit Lot:' followed by a dropdown menu showing 'Company Staff lot - \$30.00'. Below this is a tabbed interface with 'General' selected. The 'General' tab contains several settings: a checkbox for 'This lot is archived' (unchecked), a button for 'This lot is visible to users' (checked), a text input for 'Lot Name' (Company Staff lot), a text input for 'Lot Short Name' (CSL), a dropdown for 'Lot Group' (Public, highlighted with a red box), and a radio button for 'Lot Access' (Common Lot). A 'User Type' button is also visible on the right.

Lot edit page.

Dashboard Widget


The imported Mistall data can be displayed on the dashboard in a widget.

The widget is named **mistall-lot-stats**.

If the system setting for **Enable Mistall Usage** is not enabled, this widget will not appear in the edit dashboard page.

The widget shows the raw Mistall data. The names of the lot groups associated to the data will be shown beside the bar chart.

If the Mistall data is not yet associated to a lot group, it will show the Mistall lot name instead. This is the name given to the lot by Mistall.



Mistall dashboard widget.

Real-Time Maps.

The admin and user-side real-time maps have been updated to use lot groups in addition to the individual lots as pins on the map.

The functionality of the maps is not dependant on the use of Mistall in a system.

If your system doesn't have the Mistall integration enabled, the lot groups will use the data of the associated lots in place of Mistall data for the real-time maps.

Admin-Side Map.

The admin map has been updated to use lot groups.

When a lot group is clicked on, it will show the new popup.

The donut menu at the top shows the Mistall lot data, and the lot info shows the individual lot data. The bar charts below show the same lot info as above.

If the lot group has no Mistall data associated to it, it will use the collated counts of the lot info below instead.


If Mistall data is being used for the lot, it is likely it will not match the counts shown in the lot info window below. It is intentional that the information will not match.

The intention is that the client will be able to see the difference between what is physically present in the physical lot (lot group Mistall stats) and what the permits purchased within the system look

like in comparison.

For example, if the lot is physically empty but is maxed out on purchased permits, the number of available permits can be increased for that lot.

Real Time Map



Admin-Side map.


User-Side Map.

The user-side map has also been updated to use lot groups.

As before, the user map is made to appear by placing the shortcode on a client-created page.

The shortcode for the map is: **[real-time-map]**

The user-side map will now appear like this:



User-side real time map.

The donut at the top shows the Mistall data if it is present. If the lot group does not have an associated Mistall lot, it will show the collated counts of the lot info below.

The lot info shown below the donut graph is from the permit counts in the system.

Unlike the admin-side map, the information here is presented as a percentage instead of the actual numbers. This is to allow for some leeway for any inaccuracy.

The icons to the right display if the lot allows standard or temporary permits.


- Green is standard.
- Yellow is temp.

The map should be accessible for users who are not logged in. If the user is logged in, they will be able to see standard permits and temp permits, but if they are not logged in, they will only be able to see temp permits.

The book permit button now takes the user to a new page used for selecting a permit from within the selected lot group.

User-Side Lot Group Page

The lot group page shows much the same data as the regular permit page, just with the data specific to the selected lot group.



Lot group page.

At the top of the page, the same donut menu from the pop-up window on the map is shown, displaying a percentage of availability. It is calculated from the Mistall data or the lots below if there is no Mistall data for the lot group.

The lots are shown below. If the user is a guest (not logged in), they will only be able to see temporary permits on the page.

The standard permit booking button will take the user to the regular standard permit booking page, but the temporary permit booking button will take the user to the quick checkout.

This is the checkout used for QR codes and the old version of the map. It allows the user to purchase the permit and checkout immediately without adding it to their cart.

Revision #4

Created 26 June 2024 13:20:01 by Justin Gendron

Updated 26 June 2024 13:44:15 by Justin Gendron