


Disable Browser Auto-fill and Auto-Complete

How does this setting affect OPS-COM?

When using OPS-COM to complete User Profile, we are filling out forms with information for other people that is different each time. Auto-complete can become a nuisance by filling in fields you don't want filled in or even popping data that you don't notice. This data gets saved in the profile by mistake. To avoid this issue, we suggest turning off this feature in your browser.

See the screenshot below:



The screenshot displays a 'Quick Registration Form' with a section titled 'Personal Information'. Below this title is a checkbox labeled 'Allow user login and mark'. The form contains several input fields, some of which are pre-filled with placeholder text. A red speech bubble points to the 'Email Address' field, containing the text: 'Your details auto-filled in when they should be blank.' The fields and their values are as follows:

Field Label	Value
* User Type:	--- Select User Type ---
* Username:	yourUsername
* Password:	yourPassword
* Email Address:	yourEmail@yourDomain.com
Salutation:	
* First Name:	
Middle Name:	
* Last Name:	

There are also some plug-ins that can cause this issue. Password keepers for example are essentially auto-complete utilities. If you are still experiencing similar auto-complete issues after turning off auto-complete you may want to review your installed plugins to see if turning them off fixes the problem.

How to Disable Auto-fill

Please find general instructions for checking and turning off your auto-complete settings based on various browsers below:

image not found or type unknown



Turn off auto-fill in Internet Explorer

1. Click on the Tools menu icon.
2. Click on Internet Options and select the Content tab.
3. In the Auto Complete section, click on Settings.
4. Uncheck Forms and User Names and Passwords on Forms.

image not found or type unknown



Turn off auto-fill in Edge

1. Open Edge and click on the more icon (three dots) at the top right of the window.
2. Click on Settings and scroll to the bottom until you see Advanced Settings
3. Look for Save Form Entries and click on the switch to set it to off.


image not found or type unknown



Turn off auto-fill in Chrome

1. Open Chrome.
2. At the top right, click More Settings.
3. At the bottom, click Show advanced settings.
4. Under "Passwords and forms," uncheck "Enable Autofill to fill out web forms in a single click."

image not found or type unknown



Turn off auto-fill in Firefox

1. Open Firefox.
2. In the address field, type about:config and click on "I'll be careful, I'll promise"
3. Look for the following entry
"dom.forms.requestAutocomplete"
4. Double-click on it to set it's value to False.

image not found or type unknown



Turn off auto-fill in Safari

1. Click Safari, Preferences and click AutoFill.
2. Turn AutoFill on or off: Select each type of information you want Safari to fill in, and deselect the rest.
3. Change or delete autofill information: Click Edit for the type of information you want to change or delete.

Revision #2

Created 30 April 2024 07:47:36

Updated 11 September 2024 13:40:49